



Kofax TotalAgility Prerequisites

Version: 7.11.0

Date: 2022-12-30

KOFAX

© 2022 Kofax. All rights reserved.

Kofax is a trademark of Kofax, Inc., registered in the U.S. and/or other countries. All other trademarks are the property of their respective owners. No part of this publication may be reproduced, stored, or transmitted in any form without the prior written permission of Kofax.

Table of Contents

Preface.....	5
TotalAgility documentation.....	5
Full documentation set.....	5
Offline documentation.....	8
Training.....	11
Getting help with Kofax products.....	11
Chapter 1: Prerequisites.....	12
TotalAgility.....	12
Supported operating systems.....	12
Minimum hardware requirements.....	12
Software checklist.....	13
Permissions and privileges.....	13
Transformation Server.....	15
Supported operating systems.....	15
Minimum hardware requirements.....	15
Software checklist.....	16
Privileges.....	16
Non-Admin access permissions.....	16
Reporting Server.....	17
Software checklist.....	17
Permissions and privileges.....	17
Integration Server.....	17
Supported operating systems.....	17
Minimum hardware requirements.....	18
Software checklist.....	18
Kofax License Server.....	18
Software checklist.....	18
Kofax Message Connector.....	19
Chapter 2: Prerequisite utility.....	20
Run the Prerequisite utility.....	20
Appendix A: Additional details.....	22
Calculate memory requirements.....	22
MSDTC.....	22
HTTP activation for WCF services.....	23

Configure WCF activation in Windows Server 2008.....	23
Configure WCF activation in Windows Server 2012.....	24
Configure WCF activation in Windows Server 2016 and 2019.....	24
Internet.....	25
Internet browser.....	25
Kofax TotalAgility.....	25
Integration Server.....	25
Internet Information Services (IIS).....	25
IIS components activation in Windows Server 2008.....	26
IIS components activation in Windows Server 2012.....	26
IIS components activation in Windows Server 2016 and 2019.....	27
Network Protocol.....	27
Runtime prerequisites of the Transformation Server.....	27
Integration Components.....	28
KCM Proxy.....	28
Data Access.....	28
Micro Focus Content Manager.....	28
Microsoft Dynamics AX.....	28

Preface

This guide provides the following important information.


- System requirements for installing Kofax TotalAgility
- Database management requirements
- Instructions for running the prerequisite utility
- Software checklist for various installation types

Read this guide completely before installing the software.

TotalAgility documentation

To access the full documentation set online, see the [Kofax TotalAgility Documentation](#) page.

To launch the online help for the installed version of the product, click the Help icon in the application.

 When upgrading to TotalAgility 7.11.0 from an earlier version, ensure that the check box for "Import system Workspace package" is selected to view the Workspace help online; otherwise, you must import the WorkspaceHeader form from the TotalAgility Workspace package.

You can access the Kofax TotalAgility documentation online as well as [offline mode](#).

Full documentation set

A complete set of TotalAgility documentation includes the following items.

Guide/Help	Description
Administrator's Guide	Provides information for administrators who are responsible for configuring and maintaining a TotalAgility installation.
API Documentation	Includes the details of the supported APIs excluding deprecated methods, a list of supported methods for each service, and all inputs and outputs including the required fields, field types, and enumerations, any special information about the method, some coding examples, and the details behind concepts used.

Guide/Help	Description
Architecture Guide	Provides an overview of the TotalAgility architecture, covering various deployments for on-premise, on-premise multi-tenancy, and Azure environments.
Best Practices Guide	Describes the best practices to follow when using TotalAgility to improve performance, cost, maintenance, availability, and security.
Configuration Utility Guide	Provides instructions for using the Configuration Utility to update settings across various configuration files for different installation and deployment types.
Designer Help	Provides details about using TotalAgility to design business jobs and cases, assign resources, create forms, integrate with external applications, and more.
Features Guide	Provides an overview of the TotalAgility features.
Installation Guide	Provides instructions on installing TotalAgility and integrating it with other products.
Integration Server Installation Guide	Provides instructions on installing TotalAgility Integration Server and integrating it with other products.
On-Premise Multi-Tenant Installation Guide	Provides instructions on installing and configuring a TotalAgility On-Premise Multi-Tenant system.
Prerequisites Guide	Provides system requirements for installing TotalAgility, instructions for running the Pre-requisite Utility, and a software checklist for various installation types.
Release Notes	Include key details about the new and enhanced features and any changes in behavior in TotalAgility 7.11.0. It also lists any known and resolved issues in this version of TotalAgility.
Reporting Tables	Describes the Dimension and Fact tables of the Kofax Reporting data warehouse that store information related to Capture client activities of TotalAgility.
Reporting Views	Describes the sample views provided with Kofax Reporting.
Tables for Analytics	Describes the TotalAgility tables and fields used by Kofax Analytics for TotalAgility.
Tenant Management System Help	Describes how to create and manage tenants using the TotalAgility On-Premise Multi-Tenant system.
Tenant Management System Installation Guide	Provides instructions for installing the TotalAgility Tenant Management System.

Guide/Help	Description
TotalAgility Apps Help	Includes a suite of applications that allows citizen developers to configure the workflow and capture items with little to no training. TotalAgility Apps encapsulates the following applications. <ul style="list-style-type: none"> • Business Data • Quick Capture • Quick Classification • Quick RPA • Quick Rules • Quick Skins • Quick Workflow
Web Capture Control Help	Provides details for using a Web Capture control in creating multi-page documents, creating a new document in a new folder, deleting pages that have been incorrectly scanned, and more; also, describes the buttons available in a Web Capture control toolbar.
Workspace Help	Provides details for using TotalAgility to design business jobs and cases, assign resources, create forms, integrate with external applications, and more.
Other documentation	
Capture Client	Provides help for using Capture activities in TotalAgility.
Devices Help	Provides details for managing devices connected to TotalAgility.
Export Connector for TotalAgility	Provides instructions on managing an Export Connector and setting up an Export Connector for a document type.
KC/KTM Converter	Provides instructions on how to convert Kofax Capture and Kofax Transformation Modules projects into the correct format so that they can be used in TotalAgility.
Kofax .NET Restful Web Service API for Device the Client	Provides documentation for the Kofax .NET Restful Web Service API for the Device Client.
Kofax .NET Legacy API for the Device Client	Provides documentation for the Kofax .NET Legacy API for the Device Client.
Message Connector	Provides instructions on how to configure and use Kofax Message Connector.
MFP Starter Pack Getting Started Guide	Provides instructions on how to use TotalAgility to import and process the MFP Starter Pack.
MFP Administrator Guides	Describe how to prepare MFP devices to work with TotalAgility.
MFP Web Services Connector SDK Developer's Guide	Provides an overview and instructions for developing inputs with the MFP Web Services Connector Software Developer Kit (SDK). Along with this guide, the SDK provides documentation for the Web services.
Repository Browser	Provides instructions on how to use the Repository Browser to view the extraction results for a set of folders and documents.

Guide/Help	Description
Search and Matching Server	Provides documentation of the Kofax Search and Matching Server, which handles search requests from various Kofax applications for large volumes of data located at a remote site.
Transformation Designer	Provides instructions on how to use Transformation Designer to set up, store, and test projects that contain all the necessary information for processing documents.
Transformation Designer Scripting	Provides an introduction to the WinWrap Basic Editor and an overview of the available scripting events.
XDoc Browser	Provides help on using the XDoc Browser, a program that provides direct access to the document representation that is used by TotalAgility. With XDoc Browser, you can open and display an XDoc along with any referenced images for testing, demonstration, and debugging purposes.

Offline documentation

If you require offline documentation, you can download it from the [Kofax Fulfillment Site](#). For each language, a separate documentation package is available to download as a compressed file, such as TotalAgilityDocumentation_7.11.0_EN.zip for English or TotalAgilityDocumentation_7.11.0_FR.zip for French.

The English and Japanese .zip files include both help and print folders. The print folder contains PDF guides, such as the installation guide and administrator's guide. The .zip files for other languages contain a limited set of localized files.

The following procedure describes accessing TotalAgility documentation offline for English.

1. From the Kofax Fulfillment Site, download the documentation.zip file for the applicable language, such as English.
2. Extract the contents of the compressed documentation file to your local computer.
3. In the TotalAgility product installation files, inside the `Agility.Server.Web\Help` folder, create a folder for the desired language. For example, for accessing TotalAgility documentation offline for English, create the EN folder as follows:

i In a distributed environment, copy files on the Web server, and apply the Web.config changes on the Application and Web servers.

Copy the contents from the folder	Paste the contents to the folder
Designer	<pre>\\TotalAgilityInstall\Agility.Server.Web\Help \TotalAgility_designer\EN</pre> <p>i The TotalAgility installer creates the TotalAgility_designer and API folders inside the Help folder. You must manually create other folders such as Workspace and TotalAgilityApps and then copy the contents into the respective folders.</p>
Devices	<pre>\\TotalAgilityInstall\Agility.Server.Web\bin \Administrative\Help\Devices\EN</pre>

Copy the contents from the folder	Paste the contents to the folder
DocumentConverter	\\Kofax\Document Converter\web\en\WebHelp
ExportConnector	\\TotalAgilityInstall\Agility.Server.Web\Help\ExportConnector_help\EN
KCKTM_Converter	<%ProgramData%>\Kofax\Transformation\en_US\help\KCKTM_Converter
MessageConnector	\\Kofax\KIC-ED\MC\web\en\WebHelp
RepositoryBrowser	\\TotalAgilityInstall\Agility.Server.Web\Help\RepositoryBrowser\EN
SDK_Documentation	\\TotalAgilityInstall\Agility.Server.Web\Help\API\EN
TenantManagementSystem	\\TotalAgilityInstall\Agility.Server.Web.TenantManagement\TenantManagement\Help\TenantManagementSystem\EN
TotalAgilityApps	\\TotalAgilityInstall\Agility.Server.Web\Help\TotalAgilityApps\EN
TransformationDesigner	<%ProgramData%>\Kofax\Transformation\en_US\help\TransformationDesigner
WebCaptureControl	\\TotalAgilityInstall\Agility.Server.Web\Help\WebCaptureControl\EN
Workspace	\\TotalAgilityInstall\Agility.Server.Web\Help\Workspace\EN
XDocBrowser	<%ProgramData%>\Kofax\Transformation\en_US\help\XDocBrowser
Activity folder within CaptureClient Example: DocumentReviewActivity	\\TotalAgilityInstall\Agility.Server.Web\Forms\Controls\Capture\Help\DocumentReviewActivity\EN

4. Navigate to the installation folder.

For the help	Perform the following steps
<ul style="list-style-type: none"> • TotalAgility Designer • Devices • Transformation Designer • XDoc Browser • KC_KTM Converter 	<p>a. Open TotalAgility Web.config in a text editor from the following location:</p> <pre>\\TotalAgilityInstall\Agility.Server.Web</pre> <p>b. Locate the <appSettings> section and remove http://docshield.kofax.com/KTA from the key value: <add key="OnlineHelpURL" value="http://docshield.kofax.com/KTA"/>.</p>
<p>TotalAgility Export Connector</p>	<p>a. Open Agility.Server.ExportConnector.exe.config in a text editor from the following location:</p> <pre>\\TotalAgilityInstall\Agility.Server.Web\bin</pre> <p>b. Locate the <appSettings> section and remove http://docshield.kofax.com/KTA from the key value: <add key="OnlineHelpURL" value="http://docshield.kofax.com/KTA"/>.</p> <p>Alternatively, run the Configuration Utility (available from the TotalAgility Product installation files at \\TotalAgilityInstall\Utilities\ConfigurationUtility) and remove the URL for online help from the OnlinehelpURL setting.</p> <div style="border: 1px solid #add8e6; padding: 5px; margin-top: 10px;"> <p>i For the Transformation Designer, XDoc Browser, and KC_KTM Converter Help to work offline and make sure that TotalAgility is actively connected to Transformation Designer. To connect TotalAgility to Transformation Designer, log in to Transformation Designer and click File > Connections and provide the connection path.</p> </div>
<p>TotalAgility Message Connector</p>	<p>a. Open configuration.xml in a text editor from the following location:</p> <pre>\\Kofax\KIC-ED\MC\web</pre> <p>b. Locate the <OnlineHelp>1</OnlineHelp> section and replace 1 with 0.</p>
<p>TotalAgility Document Converter</p>	<p>a. Open configuration.xml in a text editor from the following location:</p> <pre>\\Kofax\Document Converter\web</pre> <p>b. Locate the <OnlineHelp>1</OnlineHelp> section and replace 1 with 0.</p>

5. Save and close the configuration file.

Clicking the Help icon will launch the help for the installed product.

Training


Kofax offers both classroom and online training to help you make the most of your product. To learn more about training courses and schedules, visit the [Kofax Education Portal](#) on the Kofax website.

Getting help with Kofax products

The [Kofax Knowledge Base](#) repository contains articles that are updated on a regular basis to keep you informed about Kofax products. We encourage you to use the Knowledge Base to obtain answers to your product questions.

To access the Kofax Knowledge Base:

1. Go to the [Kofax website](#) home page and select **Support**.
2. When the Support page appears, select **Customer Support > Knowledge Base**.

 The Kofax Knowledge Base is optimized for use with Google Chrome, Mozilla Firefox or Microsoft Edge.

The Kofax Knowledge Base provides:

- Powerful search capabilities to help you quickly locate the information you need.
Type your search terms or phrase into the **Search** box, and then click the search icon.
- Product information, configuration details, and documentation, including release news.
Scroll through the Kofax Knowledge Base home page to locate a product family. Then click the product family name to view a list of related articles. Please note that some product families require a valid Kofax Portal login to view related articles.

From the Knowledge Base home page, you can:

- Access the Kofax Community (for all customers).
Click the **Community** link at the top of the page.
- Access the Kofax Customer Portal (for eligible customers).
Click the **Support** link at the top of the page. When the Customer & Partner Portals Overview appears, click **Log in to the Customer Portal**.
- Access the Kofax Partner Portal (for eligible partners).
Click the **Support** link at the top of the page. When the Customer & Partner Portals Overview appears, click **Log in to the Partner Portal**.
- Access Kofax support commitments, lifecycle policies, electronic fulfillment details, and self-service tools.
Go to the **General Support** section, click **Support Details**, and then select the appropriate tab.

Chapter 1

Prerequisites

The primary source of information about supported operating systems and other Kofax TotalAgility requirements is the Technical Specifications document, which is available on the Kofax website at www.Kofax.com. This chapter provides additional details about Kofax TotalAgility hardware and system requirements.

TotalAgility

This section provides information about TotalAgility system requirements for the server where both the Web Server and Application Server exist.

You must install the Web Server and Application Server with the same user account.

TotalAgility is supported in virtual machine environments, such as the Hyper-V role in Windows Server 2008 R2. Each virtual machine (child partition) must have sufficient processor resources, memory, and disk resources for its TotalAgility instance.

The SQL and TotalAgility servers must run in the same time zone; otherwise, unexpected issues such as activities resetting incorrectly, may occur.

Supported operating systems

See the Technical Specifications document on the Kofax website.

Minimum hardware requirements

Component	Requirement
Processor Type	x64 Processor: AMD Opteron, AMD Athlon 64, Intel Xeon with Intel EM64T support, Intel Pentium IV with EM64T support
Processor Speed	x64 Processor: 2.6 GHz or faster
Disk Space	4 GB of available hard disk space Disk space requirements may vary with the TotalAgility components you install.
Memory	8 GB
Database	100 MB
DVD Drive	If installing from disk

Software checklist


The system performs the following software check when you run the Prerequisite utility before installing TotalAgility to ensure all required software is installed on your computer.

Web Server and Real Time Transformation Service

- Windows Operating System (Windows 2008 & above)
- Log on as a service
- IIS (ASP.NET, Windows Authentication, Static Content)
- WCF HTTP Activation

Application Server

- Windows Operating System (Windows 2008 & above)
- Log on as a service
- IIS (ASP.NET, Windows Authentication, Static Content)
- WCF HTTP Activation
- Database Creation Permissions

 Kofax Message Connector requires .NET Framework 4.8. Download .NET Framework from the Microsoft website.

See [Appendix A](#) for more information.

Web Application Server

For the Web Application Server software checks, see [Application Server](#).


Permissions and privileges

Database permissions

- The account used to connect to the databases during the installation requires rights to create the databases.
- For a newly created database, the dbo schema is the default schema and by default, TotalAgility uses the default SQL server dbo schema.
- If the installer is to overwrite pre-existing databases (as opposed to creating new databases), then the account used to connect to the database needs to have rights to delete the existing Database and create the new one.
- The account used to upgrade the databases (via installer or manually) requires ALTER permission on the database along with CONTROL permission on the installed schema.
- The service account specified during the installation is used to connect to the database at runtime. The runtime privileges required by this account are db_datareader, db_datawriter and Execute permissions.

See "Create a tenant" in the *Tenant Management System Help*.

- After TotalAgility on-premise multi-tenant installation, the account used by the Tenant Management System website must have two database accounts (Database Creator and Login Creator) when adding tenants. Database Creator must have rights to create tenant database and Login Creator must have rights to create logins for tenants. See the *Tenant Management System Help*.

 For a list of supported databases, see the Technical Specifications document, which is available on the Kofax website at www.Kofax.com.

Privileges to run Kofax TotalAgility components

The privileges required for running various Kofax TotalAgility components are based upon the "Principle of Least Privilege".

The installation privileges are different than those required to run TotalAgility. Installing TotalAgility requires administrator privileges.

All the Service accounts require certain privileges.

- Local Policies Permissions
 1. Log on as Administrator and open a Command Prompt window.
 2. Run the following command: **secpol.msc**
 3. Under Security Settings, navigate to **Local Policies**, click **User Rights Assignment**, and ensure the account has following permissions:
 - Allow logon locally
 - Log on as a service
 - Bypass traverse checking
- You must have read and write permissions on the ProgramData folder, and enumerate the network user accounts against a domain. When the AppPool user changes, permissions to the ProgramData folder must be granted manually.
- When a split Web Application server is deployed, and Kerberos is being used, enable the computer and the user account used by IIS to be trusted for delegation.
- The account under which the Transformation Server service runs must have specific [access permissions](#).
- The service account under which the Streaming service runs must have permissions to register a URL and reserve a namespace for it. If it is a non-admin account, the local machine administrator needs to do these for the service account. See the *TotalAgility Installation Guide*.
- The license service can be run under a non-admin account. The non-admin account should have permission to open a WCF listener. If it is running under a non-admin account on a non-standard port, you should reserve a namespace for it. To do so, on the Command Prompt, run the following command using an account that has administrator rights on the local machine:


```
netsh http add urlacl url=http://+:3581/SAL user=%domainuser%
netsh http add urlacl url=http://+:3581/SALMetadata user=%domainuser%"
```

- When you run the Import Connector with a non-admin account, the following permissions are required:
 - Registry Permissions: Read permissions on HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Kofax\KIC-ED\MC
 - Folder Permissions: Full control on the following folders; ProgramData\Kofax\KIC-ED\MC, Installation Folder, Temp Folder

Permissions for Active Directory Synchronization

The account used to execute the active directory synchronization (configured as a server variable) requires the following:

- Read MemberOf
- List Contents
- Read E-mail-Addresses
- Read userPrincipalName
- Read department
- Read cName
- Read DeletedObjectsContainer

 if "Referrals" are needed, the account must have permission to interrogate the same attributes across forests.

Additionally:


- The account does not need to be a Domain Admin.
- The account does not create anything in Active Directory; it is read-only.

Transformation Server

This section provides information about system requirements for installing the Transformation Server.

Supported operating systems

See the Technical Specifications document available at the [Kofax TotalAgility Documentation](#).

 Transformation Server installs some runtime prerequisites. The Prerequisite utility checks for the software which Transformation Server does not install.

Minimum hardware requirements

Component	Requirement
Processor Type	x64 Processor: AMD Opteron, AMD Athlon 64, Intel Xeon with Intel EM64T support, Intel Pentium IV with EM64T support

Component	Requirement
Memory	See Calculate memory requirements
Database	Not required

Software checklist

- Windows Operating System (Windows 2012 & above)
- Log on as a service
- DigiCert Assured ID Root CA certificate

i For a Transformation Server, .NET Framework is automatically installed if the Transformation Server is installed where you installed TotalAgility. If you install Transformation Server or Transformation Designer independent of TotalAgility, make sure the supported version of .NET Framework is already installed on that machine.

See [Appendix A](#) for more information. Also, see the [runtime prerequisites](#) for the Transformation Server.

Privileges

You must have administrator privileges to run the Transformation Server on-premise multi-tenancy on all Windows (Server) operating system.

Non-Admin access permissions

Transformation Server can be run on On-Premise using the following non-admin privileges:

Set up a user account (For example, TS_User) for Transformation Server.


- TS_User must be part of Windows Group: Users.
- TS_User must have the Local Security Policy rights: Log on as Service.
- TS_User must have full access to the log file folder configured for logging. (By default, it is the installation folder)
- TS_User must have full access to the following folders:
 - C:\ProgramData\Kofax
 - C:\Program Files (x86)\Common Files\Kofax\Server

i This folder contains "Kofax.CEBPM.CPUserver.ServiceHost.exe.config."

- TS_User must have the following rights to the database:
 - db_reader
 - db_writer
 - Execute permission

Reporting Server

Kofax Reporting provides centralized storage of historical operational metrics and audit data. Kofax Reporting includes the components such as the ETL Agent and databases.

 Due to high process utilization by Transformation Server (99%), Reporting Server is known to produce a "SQL Timeout error" when installed on the same machine as Transformation Server. Therefore, you must install Reporting Server separately from Transformation Server.

Software checklist

- Windows Operating System (Windows 2008 & above)
- Log on as a service


See [Appendix A](#) for more information.

Permissions and privileges

- The user who will run the Reporting Server must have "Log on as Service" rights. The user need not have the administrative rights.
- The user must have read and write permissions on the ProgramData folder, and enumerate the network user accounts against a domain. When the AppPool user changes, permissions to the ProgramData folder must be granted manually.
- Also, the user who is running Reporting Server is used for all communication channels where Windows authentication is used. For example, if Windows authentication is being used for SQL Server, this user must have rights on this server; otherwise, Reporting Server will not work.

Integration Server

The section provides information about Integration Server system requirements for the server where the Web Server and Application Server both reside.

 Each virtual machine (child partition) must have sufficient processor resources, memory, and disk resources for its Integration Server instance.

Each virtual machine (child partition) must have sufficient processor resources, memory, and disk resources for its Integration Server instance.

Supported operating systems

For updated information about supported operating systems and other system requirements for TotalAgility, see the Technical Specifications document available on the Kofax website at www.Kofax.com.

Minimum hardware requirements

Component	Requirement
Processor Type	x64 Processor: AMD Opteron, AMD Athlon 64, Intel Xeon with Intel EM64T support, Intel Pentium IV with EM64T support
Processor Speed	x64 Processor: 2.6 GHz or faster
Hard Disk	Minimum: 4 GB of available hard disk space Disk space requirements will vary with the Integration Server components you install.
Memory	Minimum: 8 GB
DVD Drive	If installing from disk

Software checklist

- Windows Operating System (Windows 2008 & above)
- Log on as a service
- IIS (ASP.NET, Windows Authentication, Static Content)
- WCF HTTP Activation

See [Appendix A](#) for more information.

Kofax License Server

This section provides information about the License Server.

Software checklist

To install the Kofax License Server successfully for use with Kofax TotalAgility, verify that the following prerequisites are met:

- The "Log on as a service" right must be assigned to the user running the Windows service.
- The Visual Studio C++ 2019 Redistributable x86 runtime must be installed.
- If the license server is installed separately from TotalAgility, the installation should be performed by a user with elevated privileges.

See [Appendix A](#) for more information.

Kofax Message Connector


This section following provides information about the system requirements for installing and operating Kofax Message Connector.

Component	Requirement
Disk Usage	<ul style="list-style-type: none"> • 2000 MB approximately for the application. • Additional space for temporary storage of transferred documents. (Maximum storage size supported = 250000 MB).
Supported Third Party Fax Servers	<p>Kofax Message Connector can connect and import messages from the following third-party fax servers (minimum versions listed):</p> <ul style="list-style-type: none"> • RightFax • Biscom • Kofax Communication Server <p>For information about supported versions, refer to the TotalAgility Technical Specifications document.</p> <pre data-bbox="532 926 1451 1171"> i C:\Windows\System32>regsvr32 "C:\Program Files (x86)\RightFax\Shared Files \rfaxui.dll" C:\Windows\System32>regsvr32 "C:\Program Files (x86)\RightFax\Shared Files\rfcomapi.dll" C:\Windows\System32>regsvr32 "C:\Program Files (x86)\RightFax\Shared Files \rfaxui.dll" C:\Windows\System32>regsvr32 "C:\Program Files (x86)\RightFax\Shared Files\rfcomapi.dll" </pre> <p>Manual registration is not required for RightFax client software version 10.x.</p>
Attachment Encoding	<p>Kofax Message Connector understands attachments with the following Content-Transfer- Encoding types:</p> <ul style="list-style-type: none"> • Base64 • Quoted-Printable <p>TotalAgility does not support other encoding types such as uuencode or Xxencode.</p>

Chapter 2

Prerequisite utility

Kofax TotalAgility requires certain software to be installed on your system before proceeding with the installation. You can run the Prerequisite utility for the different types of installation before installing TotalAgility to ensure all required software is installed on your computer.

 To run the Prerequisite utility, user must have administrator rights.

Run the Prerequisite utility

1. Navigate to `TotalAgility\Utilities\Pre-requisite Utility` on the installation media, right click **Agility.Installation.Server.Prerequisites** and select Run as administrator.
2. In the TotalAgility **Prerequisite Check** window, click **Next**.
The Type of Installation window appears.
3. Select the installation type on which the prerequisite check needs to be detected, such as **Web/ Application Server**.
You can run the prerequisite checks for the following installation types: Database Only, Web Server / Real Time Transformation Service, Application Server, Web / Application Server, Application Server On-Premise Multi-Tenancy, Web / Application Server On-Premise Multi-Tenancy, License Server, Integration Server, Reporting Server, and Transformation Server.
4. Click **Next**.
The Credentials window appears.
5. Enter the credentials for the user who will run TotalAgility and click **Next**.
If the user does not have "Log on as Service" rights, a warning appears on clicking **Next**.
6. In the **Database** window, select either option to create the databases:
 - To allow the installation program to automatically create databases, select **Automatically by the Installation Program** and then choose the database server mode.

SQL Server NonSSL	<ol style="list-style-type: none">a. In the Database Server box, enter a name for the database server.b. Under Security, select either option:<ul style="list-style-type: none">• Windows Authentication• SQL Server Authentication and provide the user name and password.
SQL Azure	<ol style="list-style-type: none">a. In the Database Server box, enter a name for the database server.b. Under Security, select SQL Server Authentication and provide the user name and password.

- To manually create databases, select **Manually**.
7. Click **Next**.

The "Software checks" window appears for the selected installation type. The system displays a list of required software and indicates whether the software is installed.
 8. Review the **Detected Software** list.
 - If your system does not have all the required software, the software check is completed with errors that are logged to PrerequisiteUtilityErrorLog.txt, which is created automatically. Resolve the errors and rerun the utility until the results are error free.
 - If your system has all the required software, click **Finish**.

Appendix A

Additional details

This section provides additional checks for various installation types, including prerequisites for the integration components.

Calculate memory requirements

The computer running Transformation Server must have sufficient memory to keep multiple extraction and classification groups cached in memory. Transformation Server maximizes memory utilization and uses any free memory to run and cache additional extraction processes.

In addition to the memory requirements for the operating system, memory is required for the Transformation Server based on the size of the extraction and classification groups and the number of slots you have available. To calculate the minimum amount of memory needed for Transformation Server, do the following:

1. Determine the number of slots available. During installation, Transformation Server can calculate the number of slots automatically using this formula:

Number of processor cores * 1.25

For a quad core processor, you have five slots.

You can also specify the number of slots during installation.

2. Calculate the minimum amount of memory using this formula:

200 MB + (average extraction process size * number of slots)

The extraction process size is the amount of memory needed for a single extraction process, which depends on the complexity of classification and extraction groups. Typically, these are 150–200 MB, but can be as large as 500 MB. To find out the exact sizes, examine the processes in Windows Task Manager and look for the instances of ExtractionProcess.exe.

For example, if you are processing large extraction and classification groups and have five slots of available, calculate the minimum amount of memory as shown:

200 MB + (250 MB * 5) = 1450 MB or 1.42 GB

These are minimum requirements. Additional memory can improve system performance.

MSDTC

If the Application Server and databases are installed on the same server, it is not required to start MSDTC. When you have split databases such as Main database and Archive database, or

when Application Server and databases are in a distributed environment, you require Microsoft Distributed Transaction Coordinator (MSDTC).

- The MSDTC should be enabled on the machine and the following settings should be selected:
 - Network DTC Access
 - Transaction Manager Communication (Authentication is not required)
 - Enable XA transactions
 - Enable SNA LU 6.2 Transactions
- On a Windows Server, do the following to enable the settings:
 1. Navigate to Control Panel > System and Security > Administrative Tools.
 2. Click **Component Services**.
The Component Services window appears.
 3. In the left panel, under **Console Root** expand the Component Services > Distributed Transaction Coordinator and select **Local DTC**.
 4. From the Local DTC context menu, select **Properties**.
 5. In the Local DTC Properties window, on the **Security** tab, select **Network DTC Access** and **Enable SNA LU 6.2 Transactions**.
- After the settings are completed, you should start the Distributed Transaction Coordinator service. To start MSDTC manually, on the Command Prompt window, run the following command:
`net start msdtc`. Alternatively, at Run, type Services.msc and press **Enter**. Right-click the Distributed Transaction Coordinator service and click **Start**.

HTTP activation for WCF services

- Ensure IIS is installed in the computer.
- Ensure that the .NET Framework is registered with IIS.
- Ensure that the Authentications are enabled in IIS (both Windows and Anonymous should be enabled).

Configure WCF activation in Windows Server 2008

1. Navigate to **Control Panel > Programs > Programs and Features**.
2. Click the **Turn Windows features on or off** link.
The Windows Features screen appears.
3. Expand **Microsoft .Net Framework 4.5.2 Advanced Services > WCF Services** and select **HTTP Activation**.
4. Click **OK**.
The system installs WCF on the computer. If you have installed WCF on a computer which already has ASP.NET installed, you may need to re-register ASP.NET in IIS.

Configure WCF activation in Windows Server 2012

1. Click **Server Manager** on the task bar.
The Server Manager Dashboard page appears.
2. Click the **Add roles and features** link.
The **Add Roles and Features** wizard screen appears.
3. Click **Next**.
4. Select the installation type as **Role-based or feature based installation** or **Remote Desktop Services installation** and click **Next**.
5. Select a server or virtual hard disk on which to install roles and features and click **Next**.
6. On the **Server Roles** tab, expand **Web Server (IIS)** and do the following:
 - a. Expand the **Web Server > Application Development** and select **ASP.NET 4.5.2**.
 - b. Expand **Management Tools** and select **IIS Management Console**.
7. Click **Next**. Ensure that on the **Feature** tab, **.NET Framework 4.5.2 Features** is selected and under **WCF Services**, **HTTP Activation** is selected. You can add other types of WCF Services, such as TCP Activation, Named Pipe Activation, if required.
8. Click **Next**.
9. On the **Confirmation** tab, click **Install**.

Configure WCF activation in Windows Server 2016 and 2019

1. Click **Server Manager** on the task bar.
The Server Manager Dashboard page appears.
2. Click the **Add roles and features** link.
The **Add Roles and Features** wizard screen appears.
3. Click **Next**.
4. Select the installation type as **Role-based or feature based installation** or **Remote Desktop Services installation** and click **Next**.
5. Select a server or virtual hard disk on which to install roles and features and click **Next**.
6. On the **Server Roles** tab, expand **Web Server (IIS)** and do the following:
 - a. Expand the **Web Server > Application Development** and select **ASP.NET 4.5.2**.
 - b. Expand **Management Tools** and select **IIS Management Console**.
7. Click **Next**. Ensure that on the **Feature** tab, **.NET Framework 4.8 Features** is selected and under **WCF Services**, **HTTP Activation** is selected. You can add other types of WCF Services, such as TCP Activation, Named Pipe Activation, if required.
8. Click **Next**.
9. On the **Confirmation** tab, click **Install**.

Internet

If using a shared or remote license server, you need a connection to the Internet to get the product code and serial number.

Internet browser

This section provides information on the supported browsers.


Kofax TotalAgility

Mobile forms, excluding capture-enabled forms for Scan, Document Review, Validation and Verification, support the latest version and the immediate previous version of the following browsers and their mobile equivalents:

- Edge
- Chrome
- Safari (not supported for on-premise multi-tenancy)

Capture forms support the latest version of the following browsers:

- Edge
- Chrome (32-bit)

 To view a scan-enabled form, you must install the Web Capture Service. See the *TotalAgility Installation Guide*.

You must install a PDF plug-in to view PDF files.

Integration Server

The Integration Server supports the latest and previous versions of the following browsers and their mobile equivalents:

- Edge
- Chrome

Internet Information Services (IIS)

IIS v7 or later is required.

- Add the Web server role with ASP.NET and Windows Authentication in Server Manager.
- To activate Windows Communication Foundation (WCF), install ASP.NET 4.5.2 and .NET WCF 4.5 along with IIS.

- If .NET Framework is installed before you install the IIS, you must register the .NET Framework with IIS. In the Command Prompt window, run `aspnet_regiis -i` located at `C:\Windows\Microsoft.NET\Framework64\v4.0.30319`.
If IIS is already installed, the .NET Framework registers itself with the IIS during installation.
- Use IIS Dynamics IP Restrictions for Denial of Service attacks.
- Install URL Rewrite and write the rules to prevent access to sensitive files.

 URL Rewrite is not required for the Integration Server.

IIS components activation in Windows Server 2008

1. Navigate to **Control Panel > Programs > Programs and Features**.
2. Click the **Turn Windows features on or off** link.
3. Expand **World Wide Web Services** and do the following:
 - Expand **Application Development Features** and select **ASP.NET**.
 - Expand **Common HTTP Features** and select **Static Content**.
 - Expand **Security** and select **Windows Authentication**.
4. Click **OK**.

The system installs the selected IIS components on the computer.

IIS components activation in Windows Server 2012

1. Click **Server Manager** on the task bar.
The Server Manager Dashboard page appears.
2. Click the **Add roles and features** link.
The Add Roles and Features Wizard screen appears.
3. Click **Next**.
4. Select the installation type as **Role-based or feature based installation** or **Remote Desktop Services installation** and click **Next**.
5. Select a server or virtual hard disk on which to install roles and features and click **Next**.
6. On the **Server Roles** tab, expand **Web Server (IIS)** and do the following:
 - a. Expand the **Web Server > Common HTTP Features** and select **Static Content**.
 - b. Expand the **Web Server Security** and select **Windows Authentication**.
 - c. Expand **Web Server > Application Development** and select **ASP.NET**.
7. Click **Next**. Ensure that in the **Feature** tab, **.NET Framework 4.5.2 Features** is selected and under **WCF Services**, **HTTP Activation** is selected.
8. Click **Next**.
9. On the **Confirmation** tab, click **Install**.

IIS components activation in Windows Server 2016 and 2019

1. Click **Server Manager** on the task bar.
The Server Manager Dashboard page appears.
2. Click the **Add roles and features** link.
The Add Roles and Features Wizard screen appears.
3. Click **Next**.
4. Select the installation type as **Role-based or feature based installation** or **Remote Desktop Services installation** and click **Next**.
5. Select a server or virtual hard disk on which to install roles and features and click **Next**.
6. On the **Server Roles** tab, expand **Web Server (IIS)** and do the following:
 - a. Expand the **Web Server > Common HTTP Features** and select **Static Content**.
 - b. Expand the **Web Server Security** and select **Windows Authentication**.
 - c. Expand **Web Server > Application Development** and select **ASP.NET**.
7. Click **Next**. Ensure that in the **Feature** tab, **.NET Framework 4.8 Features** is selected and under **WCF Services, HTTP Activation** is selected.
8. Click **Next**.
9. On the **Confirmation** tab, click **Install**.

Network Protocol

TCP/IP is the supported network protocol.

Runtime prerequisites of the Transformation Server

Runtime Transformation Server requires the following prerequisites.

- Microsoft .NET Framework 4.8
- MS_XML 4.0**
- Visual Studio vc++ redistributables**
 - vcredist_2008_SP1_x86
 - vcredist_2010_SP1_x86
 - vcredist_2010_SP1_x64
 - vcredist_2013_x86
 - vcredist_2013_x64
 - vcredist_20017_x86
 - vcredist_20017_x64

**Automatically installed if currently not available on machine.

Integration Components


KCM Proxy

Before installing the KCM Proxy, install URL Rewrite on the Web server in either of the following ways:

- Download from the Microsoft website.
- Use the Web Platform Installer (Web PI). If using a Web PI, either install it manually or run the following command from a Command Prompt window:


```
C:\<install location>\Web Platform Installer\WebPICmd"\install\accepteula  
\Products:ARRv3_0
```

When using the KCM (Kofax Communication Manager) Interactive form control, browsers prevent cross-domain HTTP requests to the KCM server made from a form hosted on the Kofax TotalAgility server. The KCM Proxy allows cross-domain communication and uses the KCM control to generate documents.

 To use KCM functionality, you must run the installer on every Web server that is in use. Ensure that the Microsoft plug-in, Web Platform Installer, is installed before you add the KCM Proxy Web server.

Data Access

Kofax TotalAgility supports the Oracle ODAC Driver which is an OLEDB provider. The driver depends on the SQL server. If it is a 64-bit server, then you must use the 64-bit version of the driver, otherwise, use the 32-bit version. TotalAgility supports both versions depending on the platform version.

 You can still download and install Oracle 32-bit drivers.


Micro Focus Content Manager

- IIS
- .NET Framework
- TotalAgility (optional)

Microsoft Dynamics AX

- Users created in TotalAgility must have Deployment Administrator rights.
- If a user does not use the default Deployment Administrator to install the TotalAgility Dynamics AX integration, the user must meet the following conditions:
 - Be the system administrator in AX
 - Have full CAL access.

Failure to meet the preceding criteria generates the "System unable to process request" error message during installation.

 If you are using 64 bit operating system and Dynamics AX 2009 32 bit application, enable the Application Pool account associated with the DAX Communicator site. In the IIS Manager, click Application Pools> DAXAppPool > AdvancedSettings and set True for Enable 32-Bit Applications.